


DOUGLAS

WESTERN UNITED STATES 1:250,000



Prepared by the U.S. Army Topographic Command (KOSK), Washington, D.C. Compiled in 1961 by photogrammetric methods and from United States quadrangles 1:50,000, 1:50,000. Planimeter revised from aerial photographs taken 1957-58. Photographs field annotated 1958-59. Revised by the U.S. Geological Survey 1970.

Transverse Mercator Projection, 10,000-meter Universal Transverse Mercator grid, zone 12. 100,000-foot grid ticks based on Arizona coordinate system, east zone and New Mexico coordinate system, west zone. 1927 North American datum to place on the predicted North American Datum 1983 move the projection lines 10 meters south and 58 meters east.

Location of geodetic control established by government agencies is shown on corresponding 1:250,000-scale Geodetic Control Diagram.

There may be private intrusions within the boundaries of the National or State reservations shown on this map.

LEGEND

Figures in red denote approximate distances in miles between stars

POPULATED PLACES

Over 500,000
100,000 to 500,000
25,000 to 100,000
5,000 to 25,000
1,000 to 5,000
Less than 1,000

RAILROADS

Standard gauge
Narrow gauge
Interchange

BOUNDARIES


State
County
Park or reservation

ROADS

Primary, all-weather, hard surface
Secondary, all-weather, hard surface
Light-duty, all-weather, improved surface
Fair or dry weather, unimproved surface
Trail

Other

Landmark: School, Church, Other, etc.
Mine
Spot elevation in feet
Marsh or swamp
Intermittent or dry stream
Power line



SECTIONIZED TOWNSHIP

6	5	4	3	2	1
7	8	9	10	11	12
18	17	16	15	14	13
19	20	21	22	23	24
30	29	28	27	26	25
31	32	33	34	35	36

GRID ZONE DESIGNATION

128

100,000 M. SQUARE IDENTIFICATION

WL XL YL
WK XK YK

TO GIVE A STANDARD REFERENCE ON THIS SHEET TO NEAREST 100 METERS

SAMPLE POINT: RANCH

1. Read letters identifying 100,000 meter square in which the point lies.
2. Locate from VERTICAL grid line to LEFT of point and read LARGE figure indicating the line within is the top or bottom margin, or on the line itself.
3. Estimate meters from grid line to point. Locate from HORIZONTAL grid line BELOW point and read LARGE figure indicating the line within is the top or bottom margin, or on the line itself.
4. Estimate meters from grid line to point.

EXAMPLE: 3420000
If reporting beyond 10° in any direction, prefix Grid Zone Designation, etc.

DOUGLAS, ARIZONA NEW MEXICO

1959
REVISED 1970